



**Note: This API call is for DOS and Win16 personality only. Use [Family API](#) for portability.**

2018/09/07 05:04 · prokushev · [0 Comments](#)

# Int 21H, AH=34H

## Version

2 and higher

## Brief

GET ADDRESS OF INDOS FLAG

## Family API

## Input

AH = 34h

## Return

ES:BX → one-byte InDOS flag

## Notes

this function executes on the DOS stack, and thus cannot be called while another DOS function is already executing; you should use this function once at the beginning of the program and store the returned pointer rather than calling it when requiring DOS access the value of InDOS is incremented whenever an INT 21 function begins and decremented whenever one completes during an INT 28 call, it is safe to call some INT 21 functions even though InDOS may be 01h instead of zero InDOS alone is not sufficient for determining when it is safe to enter DOS, as the critical error handling decrements InDOS and

increments the critical error flag for the duration of the critical error. Thus, it is possible for InDOS to be zero even if DOS is busy.

SMARTDRV 4.0 sets the InDOS flag while flushing its buffers to disk, then zeros it on completion

the critical error flag is the byte immediately following InDOS in DOS 2.x, and the byte BEFORE the InDOS flag in DOS 3.0+ and DR DOS 3.41+ (except COMPAQ DOS 3.0, where the critical error flag is located 1AAh bytes BEFORE the critical section flag)

for DOS 3.1+, an undocumented call exists to get the address of the critical error flag (see AX=5D06h)

this function was undocumented prior to the release of DOS 5.0.

## See also

AX=5D06h,AX=5D0Bh,INT 15/AX=DE1Fh,INT 28

## Note

Text based on [Ralf Brown Interrupt List Release 61](#)

<b>DOS API</b>	
Process manager	INT 20H, <b>INT 21H</b> : 00H, 25H, 26H, 31H, 34H, 35H, 4BH, 4CH, 4DH, 50H, 51H, 52H, 55H, 62H, INT 22H, INT 27H, INT 28H
File manager	INT 25H, INT 26H, <b>INT 21H</b> : 0DH, 0EH, 0FH, 10H, 11H, 12H, 13H, 14H, 15H, 16H, 17H, 19H, 1AH, 1BH, 1CH, 21H, 22H, 23H, 24H, 27H, 28H, 29H, 2EH, 2FH, 32H, 3305H, 36H, 39H, 3AH, 3BH, 3CH, 3DH, 3EH, 3FH, 40H, 41H, 42H, 4300H, 4301H, 45H, 45H, 46H, 4EH, 4FH, 54H, 56H, 5700H, 5701H, 5AH, 5BH, 5c00H, 5c01H, 60H, 67H, 68H, 6900H, 6901H, 6AH, 6CH
Character Device I/O	INT 29H, <b>INT 21H</b> : 01H, 02H, 03H, 04H, 05H, 06H, 07H, 08H, 09H, 0AH, 0BH, 0AH, 0CH, 5D07H, 5D08H, 5D09H, 5D0AH
Signals	INT 23H, INT 24H, <b>INT 21H</b> : 3300H, 3301H, 3302H
Memory manager	<b>INT 21H</b> : 48H, 49H, 4AH, 5800H, 5801H, 5802H, 5803H
Date and Time	<b>INT 21H</b> : 2AH, 2BH, 2CH, 2DH
Misc	<b>INT 21H</b> : 30H, 3306H, 3700H, 3701H, 3702H, 3703H, 59H
NLS	<b>INT 21H</b> : 3303H, 3304H, 3800H, 3801H, 6300H, 6301H, 6301H, 6500H, 6501H, 6502H, 6503H, 6504H, 6505H, 6506H, 6507H, 6520H, 6521H, 6522H, 6523H, 65A0H, 65A1H, 65A2H, 6601H, 6602H
Devices	<b>INT 21H</b> : 4400H, 4401H, 4402H, 4403H, 4404H, 4405H, 4406H, 4407H, 4408H, 4409H, 440AH, 440BH, 440CH, 440DH, 440EH, 440FH, 4410H, 4411H, 53H
Network	<b>INT 21H</b> : 5E00H, 5E01H, 5E02H, 5E03H, 5E04H, 5E05H, 5F00H, 5F01H, 5F02H, 5F03H, 5F04H, 5F05H, 5F07H, 5F08H


<b>osFree Macro Library</b>	
Video I/O	@SetMode @SetCurSz @SetCurPos @GetCur @SetPage @ScrollUp @ScrollDn @Scroll @GetChAtr @PutChAtr @PutCh @SetPalet @SetColor @SetDot @GetDot @WrtTTY @VideoState @GetMode @GetDisplay @GetVideoState @GetEGAInfo @Cls
Hardware info	@Equipment @MemSize
Serial I/O	@AuxInit @AuxSendChar @AuxRecieveChar @AuxStatus
Tape I/O	@TapeOn @TapeOff @TapeRead @TapeWrite
Keyboard I/O	@KbdStatus @CharIn @CharPeek
Printer I/O	@PrnPrint @PrnInit @PrnStatus
Disk I/O	@DskReset @DskStatus @DskRead @DskWrite @DskVerify @DskFormat
Date and Time	@SetTime @GetTime
Mouse	@MouInit @MouShowPointer @MouStatus @MouSetPos @MouSetMickey @MouRegion
Memory manager	@ModBlok SET_BLOCK

2022/10/04 14:28 · prokushev · 0 Comments

2018/09/04 17:23 · prokushev · 0 Comments

<b>Family API</b>		
DOS	Process Manager	DosBeep DosExit DosSleep DosExecPgm
	File Manager	DosChDir DosChgFilePtr DosClose DosDelete DosDupHandle DosMkDir DosMove DosQCurDir DosQCurDisk DosSetFileMode DosOpen DosQFileInfo DosRead DosQFileMode DosQFSInfo DosQVerify DosRmdir DosSelectDisk DosFindClose DosFindFirst DosFindNext DosSetFileInfo DosSetVerify DosWrite DosFileLocks DosSetFHandState DosNewSize DosBufReset DosQFHandState DosSetFSinfo DosShutdown
	Memory Manager	DosFreeSeg DosSubAlloc DosSubFree DosSubSet DosAllocHuge DosAllocSeg DosReallocHuge DosReallocSeg DosGetHugeShift DosCreateCSAlias
	NLS	DosCaseMap DosGetCtryInfo DosGetDBCSEv DosSetCtryCode DosGetCollate DosGetMessage DosInsMessage DosPutMessage
	Date and Time	DosSetDateTime DosGetDateTime
	Devices	DosDevConfig DosDevIOct1 DosDevIOct2
	Signals	DosHoldSignal DosSetSigHandler
	Misc	BadDynLink DosGetEnv DosGetMachineMode DosGetVersion DosError DosErrClass DosSetVec
KBD		KbdCharIn KbdFlushBuffer KbdGetStatus KbdSetStatus KbdStringIn KbdPeek
VIO		VioGetBuf VioGetConfig VioGetCurPos VioGetCurType VioGetPhysBuf VioReadCellStr VioReadCharStr VioScrollUp VioScrollDn VioScrollLf VioScrollRt VioScrUnLock VioSetCurPos VioSetCurType VioSetMode VioGetMode VioShowBuf VioWrtCellStr VioWrtCharStr VioWrtCharStrAtt VioWrtNAttr VioWrtNCell VioWrtNChar VioWrtTTY VioScrLock VioPopUp
Tools		BIND
Modules		DOSCALLS.DLL VIOCALLS.DLL KBDCALLS.DLL MSG.DLL
Libraries		API.LIB OS2386.LIB FAPI.LIB DOSCALLS.LIB SUBCALLS.LIB

2018/08/25 15:05 · prokushev · 0 Comments



From:

<http://www.osfree.su/doku/> - **osFree wiki**

Permanent link:

<http://www.osfree.su/doku/doku.php?id=en:docs:dos:api:int21:34&rev=1607496175>

Last update: **2020/12/09 06:42**

