



Note: This API call is for DOS and Win16 personality only. Use [Family API](#) for portability.

2018/09/07 05:04 · prokushev · [0 Comments](#)

Int 21H, AH=5FH, AL=05H

Version

4 and higher

Brief

GET EXTENDED REDIRECTION LIST ENTRY

Family API

Input

```
AX = 5F05h
BX = redirection list index
DS:SI -> buffer for ASCIZ source device name
ES:DI -> buffer for destination ASCIZ network path
```

Return

```
CF set on error
AX = error code (see #01680 at AH=59h/BX=0000h)
CF clear if successful
AX = server's network process ID handle (10NET)
BH = device status flag (bit 0 clear if valid)
BL = device type (03h if printer, 04h if drive)
CX = stored parameter value (user data) from AX=5F03h
BP = NETBIOS local session number
DS:SI buffer filled
ES:DI buffer filled
```

Macro

Notes

The DS:SI string must be either a local device name, a drive letter followed by a colon, or a network directory beginning with two backslashes. The DOS kernel calls INT 2F/AX=111Eh with AX on top of the stack. Also supported by Banyan VINES, LANtastic, and 10NET. For NetWare, if only a server name is specified (i.e. "\\SERVER"), the connection to that server will be closed

See also

The local session number allows sharing the redirector's session number. If an error is caused on the NETBIOS LSN, the redirector may be unable to correctly recover from errors. The DOS kernel calls INT 2F/AX=111Eh with AX on top of the stack. Supported by DR DOS 5.0. Also supported by 10NET v5.0

Note

Text based on [Ralf Brown Interrupt List Release 61](#)

| DOS API | |
|----------------------|--|
| Process manager | INT 20H, INT 21H : 00H, 25H, 26H, 31H, 34H, 35H, 4BH, 4CH, 4DH, 50H, 51H, 52H, 55H, 62H, INT 22H, INT 27H, INT 28H |
| File manager | INT 25H, INT 26H, INT 21H : 0DH, 0EH, 0FH, 10H, 11H, 12H, 13H, 14H, 15H, 16H, 17H, 19H, 1AH, 1BH, 1CH, 21H, 22H, 23H, 24H, 27H, 28H, 29H, 2EH, 2FH, 32H, 3305H, 36H, 39H, 3AH, 3BH, 3CH, 3DH, 3EH, 3FH, 40H, 41H, 42H, 4300H, 4301H, 45H, 45H, 46H, 4EH, 4FH, 54H, 56H, 5700H, 5701H, 5AH, 5BH, 5c00H, 5c01H, 60H, 67H, 68H, 6900H, 6901H, 6AH, 6CH |
| Character Device I/O | INT 29H, INT 21H : 01H, 02H, 03H, 04H, 05H, 06H, 07H, 08H, 09H, 0AH, 0BH, 0AH, 0CH, 5D07H, 5D08H, 5D09H, 5D0AH |
| Signals | INT 23H, INT 24H, INT 21H : 3300H, 3301H, 3302H |
| Memory manager | INT 21H : 48H, 49H, 4AH, 5800H, 5801H, 5802H, 5803H |
| Date and Time | INT 21H : 2AH, 2BH, 2CH, 2DH |
| Misc | INT 21H : 30H, 3306H, 3700H, 3701H, 3702H, 3703H, 59H |
| NLS | INT 21H : 3303H, 3304H, 3800H, 3801H, 6300H, 6301H, 6301H, 6500H, 6501H, 6502H, 6503H, 6504H, 6505H, 6506H, 6507H, 6520H, 6521H, 6522H, 6523H, 65A0H, 65A1H, 65A2H, 6601H, 6602H |
| Devices | INT 21H : 4400H, 4401H, 4402H, 4403H, 4404H, 4405H, 4406H, 4407H, 4408H, 4409H, 440AH, 440BH, 440CH, 440DH, 440EH, 440FH, 4410H, 4411H, 53H |
| Network | INT 21H : 5E00H, 5E01H, 5E02H, 5E03H, 5E04H, 5E05H, 5F00H, 5F01H, 5F02H, 5F03H, 5F04H, 5F05H, 5F07H, 5F08H |

| osFree Macro Library | |
|-----------------------------|--|
| Video I/O | @SetMode @SetCurSz @SetCurPos @GetCur @SetPage @ScrollUp @ScrollDn @Scroll @GetChAtr @PutChAtr @PutCh @SetPalet @SetColor @SetDot @GetDot @WrtTTY @VideoState @GetMode @GetDisplay @GetVideoState @GetEGAInfo @Cls |
| Hardware info | @Equipment @MemSize |
| Serial I/O | @AuxInit @AuxSendChar @AuxRecieveChar @AuxStatus |
| Tape I/O | @TapeOn @TapeOff @TapeRead @TapeWrite |
| Keyboard I/O | @KbdStatus @CharIn @CharPeek |
| Printer I/O | @PrnPrint @PrnInit @PrnStatus |
| Disk I/O | @DskReset @DskStatus @DskRead @DskWrite @DskVerify @DskFormat |
| Date and Time | @SetTime @GetTime |
| Mouse | @MouInit @MouShowPointer @MouStatus @MouSetPos @MouSetMickey @MouRegion |
| Memory manager | @ModBlok SET_BLOCK |

2022/10/04 14:28 · prokushev · 0 Comments

2018/09/04 17:23 · prokushev · 0 Comments

| Family API | | |
|-------------------|-----------------|--|
| DOS | Process Manager | DosBeep DosExit DosSleep DosExecPgm |
| | File Manager | DosChDir DosChgFilePtr DosClose DosDelete DosDupHandle DosMkDir DosMove DosQCurDir DosQCurDisk DosSetFileMode DosOpen DosQFileInfo DosRead DosQFileMode DosQFSInfo DosQVerify DosRmdir DosSelectDisk DosFindClose DosFindFirst DosFindNext DosSetFileInfo DosSetVerify DosWrite DosFileLocks DosSetFHandState DosNewSize DosBufReset DosQFHandState DosSetFSinfo DosShutdown |
| | Memory Manager | DosFreeSeg DosSubAlloc DosSubFree DosSubSet DosAllocHuge DosAllocSeg DosReallocHuge DosReallocSeg DosGetHugeShift DosCreateCSAlias |
| | NLS | DosCaseMap DosGetCtryInfo DosGetDBCSEv DosSetCtryCode DosGetCollate DosGetMessage DosInsMessage DosPutMessage |
| | Date and Time | DosSetDateTime DosGetDateTime |
| | Devices | DosDevConfig DosDevIOct1 DosDevIOct2 |
| | Signals | DosHoldSignal DosSetSigHandler |
| | Misc | BadDynLink DosGetEnv DosGetMachineMode DosGetVersion DosError DosErrClass DosSetVec |
| KBD | | KbdCharIn KbdFlushBuffer KbdGetStatus KbdSetStatus KbdStringIn KbdPeek |
| VIO | | VioGetBuf VioGetConfig VioGetCurPos VioGetCurType VioGetPhysBuf VioReadCellStr VioReadCharStr VioScrollUp VioScrollDn VioScrollLf VioScrollRt VioScrUnLock VioSetCurPos VioSetCurType VioSetMode VioGetMode VioShowBuf VioWrtCellStr VioWrtCharStr VioWrtCharStrAtt VioWrtNAttr VioWrtNCell VioWrtNChar VioWrtTTY VioScrLock VioPopUp |
| Tools | | BIND |
| Modules | | DOSCALLS.DLL VIOCALLS.DLL KBDCALLS.DLL MSG.DLL |
| Libraries | | API.LIB OS2386.LIB FAPI.LIB DOSCALLS.LIB SUBCALLS.LIB |

2018/08/25 15:05 · prokushev · 0 Comments

From:
<http://www.osfree.su/doku/> - **osFree wiki**

Permanent link:
<http://www.osfree.su/doku/doku.php?id=en:docs:dos:api:int21:5f:05&rev=1628216909>

Last update: **2021/08/06 02:28**

